



## Amethyst Gatefold album



By: Yvanca van Welt

© 2020 Scrap and Coffee. All rights reserved. This project information may be created/constructed for personal use only. No part of this project information may be reproduced, distributed, or transmitted in any form or by any means, including photocopying, recording, or other electronic or mechanical methods, without the prior written permission of the publisher, except in the case of brief quotations embodied in critical reviews and certain other non-commercial uses permitted by copyright law. For permission requests, write to the publisher, via email at [scrapandcoffee@gmail.com](mailto:scrapandcoffee@gmail.com)

## Supply list

- Cardstock 80 lb 12"x 12" 2 packages of 25 sheets
- Chipboard medium weight 12"x 12" 3 sheets
- Double sided tape 3/8" and 1/4"
- Wet glue like art glitter glue
- Tyvek
- Acetate .007
- Patterned paper of your choice (I've used Amethyst by Kaisercraft combined with aluminium foil cardstock by Recollections))

### OPTIONAL

- Magnets
- Photo turns / frame turns (used as swing closures) combined with brads.

### TOOLS

- Paper trimmer
- Score board / scoring stylus
- Bone folder
- Scissors
- Ruler
- Pencil
- Craft knife / utility knife

### Basic Rules:

- Apply your tape or glue on the indented side (score line) unless specifically stated otherwise.
- Fold on your score line towards the bumpy side of the score line.

## Cutting guide

### **Cover**

#### **Outside cover:**

Cut 1 piece of chipboard 9" x 9"

Cut 2 pieces of chipboard 9" x 2.50"

Cut 2 pieces of chipboard 9" x 4.50"

Cut 2 pieces of cardstock 12" x 11"

Cut 1 piece of cardstock 11" x 6"

Optional:

Cut 4 pieces of Tyvek 9" x 2.25" (Strengthen spine gussets.)

Cut 2 pieces of cardstock 9" x 8-7/8" (clean up inside cover)

#### **Inner spine:**

Cut 1 piece of chipboard 8.75" x 2-3/8"

Cut 1 piece of chipboard 8.75" x 2.25"

\* If you want a little space between binding and chipboard edge cut the pieces to 8-7/8" instead of 8.75"

Cut 1 piece of cardstock 10.75" x 5-3/8"

Cut 1 piece of cardstock 10.75" x 5.25"

#### **Window frame:**

Cut 3 pieces of chipboard 4-7/8" x 4-7/8"

Draw a 5/8" frame on 2 of these pieces.

Cut 2 pieces of cardstock 6" x 6"

Cut 1 piece of cardstock 4.75" x 4.75"

Cut 1 piece of acetate 4.75" x 4.75"

#### **Binding 1: (3 hinges) goes on 2-3/8" inner spine**

Cut 1 piece of cardstock 9.75" x 8.75"

Align the 9.75" side along the top of the scoreboard and score at:

1.50" | 2-3/8" | 3.25" | 4" | 4-7/8" | 5.75" | 6.50" | 7-3/8" | 8.25"

#### **Binding 2: (2 hinges) goes on 2.25" inner spine**

Cut 1 piece of cardstock 8.25" x 8.75"

Align the 8.25" side along the top of the scoreboard and score at:

2" | 2-7/8" | 3.75" | 4.50" | 5-3/8" | 6.25"

## **Pages (cardstock)**

### **Page 1**

Cut 1 piece 8.75" x 8.75"

Cut 1 piece 9.75" x 6.75"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

#### **Photo mat:**

Cut 1 piece 8-3/8" x 7-3/8"

### **Page 2**

Cut 1 piece 8.75" x 6.75"

Cut 1 piece 9.75" x 6.75"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

#### **Photo mat:**

Cut 1 piece 8-3/8" x 6-5/8"

### **Page 3**

#### **Binding page**

Cut 1 piece 8.75" x 8.25"

Cut 1 piece 9.75" x 3.50"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

Acetate: Cut 1 piece 4.25" x 3"

#### **Stacked pocket**

Cut 1 piece 9.75" x 3"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

Align the 3" side along the top of the scoreboard and score at: 0.50"

Acetate: Cut 1 piece 4.25" x 2-7/8"

#### **Large photo flap**

Cut 1 piece 7.75" x 7.25"

Align the 7.75" side along the top of the scoreboard and score at: 0.50"

#### **Front of page**

##### **Additional flaps**

Cut 1 piece 8.75" x 6.75"

Align the 6.75" side along the top of the scoreboard and score at: 0.50"

Apply tape on the **Bumpy** side

Cut 1 piece 8.75" x 4.75"

Align the 4.75" side along the top of the scoreboard and score at: 0.50"

##### **Waterfall**

Cut 1 piece 12" x 8"

Align the 12" side along the top of the scoreboard and score at: 5.75" and 6.25"

### **Pocket option 1**

Cut 1 piece 9" x 3.25"

Align the 9" side along the top of the scoreboard and score at: 0.50" and 8.50"

Align the 3.25" side along the top of the scoreboard and score at: 0.50"

Acetate: Cut 1 piece 7.50" x 2.50"

Use envelope punch board to punch on the 7.50" side at: 1.25" from both sides.

### **Pocket option 2**

Cut 1 piece 9" x 4.25"

Align the 9" side along the top of the scoreboard and score at: 0.50" and 8.50"

Align the 4.25" side along the top of the scoreboard and score at: 0.50"

Acetate: Cut 1 piece 7.50" x 3.25"

Make a 5/8" frame in the pocket.

## **Page 4**

### **Binding page**

Cut 1 piece 8.75" x 6.25"

Cut 1 piece 9.75" x 6.25"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

### **Front of page**

#### **Photo flaps**

Cut 2 pieces 6-5/8" x 4.25"

Align the 6-5/8" side along the top of the scoreboard and score at: 0.50"

#### **Side pockets**

Cut 2 pieces 5.25" x 4.75"

Align the 5.25" side along the top of the scoreboard and score at: 0.50" and 4.75"

Align the 4.75" side along the top of the scoreboard and score at: 0.50"

#### **Small pockets**

Cut 2 pieces 5.25" x 2.50"

Align the 5.25" side along the top of the scoreboard and score at: 0.50" and 4.75"

Align the 2.50" side along the top of the scoreboard and score at: 0.50"

Acetate: Cut 2 pieces 4" x 1-7/8"

### **Back of page**

#### **Photo flaps**

Cut 2 pieces 7.25" x 5.75"

Align the 5.75" side along the top of the scoreboard and score at: 0.50"

#### **Pocket**

Cut 1 piece 7" x 4"

Align the 7" side along the top of the scoreboard and score at: 0.50" and 6.50"

Align the 4" side along the top of the scoreboard and score at: 0.50"

Acetate: Cut 1 piece 3" x 3.50"

**Photo mat:**

Cut 1 piece 8-3/8" x 6-1/8"

**Page 5****Binding page**

Cut 1 piece 8.75" x 8.25"

Cut 1 piece 9.75" x 6.75"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

Cut 1 piece 8.75" x 5.25"

Align the 5.25" side along the top of the scoreboard and score at: 0.50"

Apply tape on the **Bumpy** side

**Front of page****Side pockets**

Cut 2 pieces 6.25" x 5-3/8"

Align the 5-3/8" side along the top of the scoreboard and score at: 0.50" and 4-7/8"

Align the 6.25" side along the top of the scoreboard and score at: 0.50"

Acetate: cut 1 piece 5.25" x 3-7/8"

**Photo flap:**

Cut 1 piece 7.75" x 5.25"

Align the 7.75" side along the top of the scoreboard and score at: 0.50"

**Backside of page****Photo flaps**

Cut 1 piece 7.25" x 6.25"

Align the 6.25" side along the top of the scoreboard and score at: 0.50"

Cut 2 pieces 7.25" x 5.75"

Align the 5.75" side along the top of the scoreboard and score at: 0.50"

**Photo mat:**

Cut 1 piece 8-3/8" x 7-3/8"

**Page 6****Binding page**

Cut 1 piece 8.75" x 6.25"

Cut 1 piece 9.75" x 6.25"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

**Front of page****Photo flaps**

Cut 2 pieces 6-1/8" x 5.50"

Align the 5.50" side along the top of the scoreboard and score at: 0.50"

Cut 2 pieces 6.75" x 4.25"

Align the 6.75" side along the top of the scoreboard and score at: 0.50"

#### **Pocket on flap**

Cut 1 piece 5.25" x 2.75"

Align the 5.25" side along the top of the scoreboard and score at: 0.50" and 4.75"

Align the 2.75" side along the top of the scoreboard and score at: 0.50"

Acetate: cut 1 piece 2-1/8" x 2-1/8"

#### **Back of page**

##### **Large photo flap**

Cut 1 piece 7.25" x 5.75"

Align the 5.75" side along the top of the scoreboard and score at: 0.50"

##### **Stacked pocket**

Cut 1 piece 7" x 3.50"

Align the 7" side along the top of the scoreboard and score at: 0.50" and 6.50"

Align the 3.50" side along the top of the scoreboard and score at: 0.50"

Acetate: cut 1 piece 5.75" x 2-5/8"

Cut 1 piece 7" x 2.75"

Align the 7" side along the top of the scoreboard and score at: 0.50" and 6.50"

Align the 2.75" side along the top of the scoreboard and score at: 0.50"

#### **Photo mat:**

Cut 1 piece 8-3/8" x 6-1/8"

## **Page 7**

#### **Binding page**

Cut 1 piece 8.75" x 8.25"

Cut 1 piece 9.75" x 5.75"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

Cut 1 piece of acetate 5-1/8" x 8.25"

Cut 1 piece 8.75" x 8.50"

Align the 8.50" side along the top of the scoreboard and score at: 0.50"

Apply tape on the **Bumpy** side

#### **Front of page**

##### **Bellyband**

Cut 1 piece 9.75" x 4.75"

Align the 9.75" side along the top of the scoreboard and score at: 0.50" and 9.25"

##### **Pocket on bellyband**

Cut 1 piece 5.75" x 4.25"

Align the 5.75" side along the top of the scoreboard and score at: 0.50" and 5.25"

Align the 4.25" side along the top of the scoreboard and score at: 0.50"

**Closure for pocket**

Cut 1 piece 4.75" x 2.50"

Align the 2.50" side along the top of the scoreboard and score at: 0.50"

**Inside of page****Photo flaps**

Cut 1 piece 6.25" x 4.75"

Align the 4.75" side along the top of the scoreboard and score at: 0.50"

Cut 1 piece 6.75" x 4.25"

Align the 6.75" side along the top of the scoreboard and score at: 0.50"

**Backside page****Large pocket**

Cut 1 piece 8-7/8" x 6.75"

Align the 8-7/8" side along the top of the scoreboard and score at: 0.50" and 8-3/8"

Align the 6.75" side along the top of the scoreboard and score at: 0.50"

**Photo flaps**

Cut 2 pieces 6.25" x 4.75"

Align the 4.75" side along the top of the scoreboard and score at: 0.50"

Acetate: cut 1 piece 3.25" x 3.75"

**Photo mat:**

Cut 2 pieces 8-3/8" x 7-3/8"

**Back inside cover**

Cut 1 piece 8-7/8" x 8-5/8" (clean up inside cover)

Cut 3 pieces 12" x 7.25"

Align the 12" side along the top of the scoreboard and score at: 5.75" and 6.25"